

HDFS File System Shell Guide

Table of contents

1 Overview.....	3
1.1 cat	3
1.2 chgrp	3
1.3 chmod	3
1.4 chown	4
1.5 copyFromLocal.....	4
1.6 copyToLocal.....	4
1.7 count	4
1.8 cp	4
1.9 du.....	5
1.10 dus	5
1.11 expunge	5
1.12 get	5
1.13 getmerge	6
1.14 ls.....	6
1.15 lsr.....	6
1.16 mkdir	7
1.17 moveFromLocal	7
1.18 moveToLocal.....	7
1.19 mv	7
1.20 put	8
1.21 rm	8
1.22 rmr	8
1.23 setrep	9

1.24 stat	9
1.25 tail	9
1.26 test	9
1.27 text	10
1.28 touchz	10

1. Overview

The FileSystem (FS) shell is invoked by `bin/hadoop fs <args>`. All FS shell commands take path URIs as arguments. The URI format is *scheme://authority/path*. For HDFS the scheme is *hdfs*, and for the local filesystem the scheme is *file*. The scheme and authority are optional. If not specified, the default scheme specified in the configuration is used. An HDFS file or directory such as */parent/child* can be specified as *hdfs://namenodehost/parent/child* or simply as */parent/child* (given that your configuration is set to point to *hdfs://namenodehost*). Most of the commands in FS shell behave like corresponding Unix commands. Differences are described with each of the commands. Error information is sent to *stderr* and the output is sent to *stdout*.

1.1. cat

Usage: `hadoop fs -cat URI [URI ...]`

Copies source paths to *stdout*.

Example:

- `hadoop fs -cat hdfs://nn1.example.com/file1
hdfs://nn2.example.com/file2`
- `hadoop fs -cat file:///file3 /user/hadoop/file4`

Exit Code:

Returns 0 on success and -1 on error.

1.2. chgrp

Usage: `hadoop fs -chgrp [-R] GROUP URI [URI ...]`

Change group association of files. With `-R`, make the change recursively through the directory structure. The user must be the owner of files, or else a super-user. Additional information is in the [HDFS Admin Guide: Permissions](#).

1.3. chmod

Usage: `hadoop fs -chmod [-R] <MODE[,MODE]... | OCTALMODE> URI
[URI ...]`

Change the permissions of files. With `-R`, make the change recursively through the directory structure. The user must be the owner of the file, or else a super-user. Additional information is in the [HDFS Admin Guide: Permissions](#).

1.4. chown

Usage: `hadoop fs -chown [-R] [OWNER][:[GROUP]] URI [URI]`

Change the owner of files. With `-R`, make the change recursively through the directory structure. The user must be a super-user. Additional information is in the [HDFS Admin Guide: Permissions](#).

1.5. copyFromLocal

Usage: `hadoop fs -copyFromLocal <localsrc> URI`

Similar to [put](#) command, except that the source is restricted to a local file reference.

1.6. copyToLocal

Usage: `hadoop fs -copyToLocal [-ignorecrc] [-crc] URI <localdst>`

Similar to [get](#) command, except that the destination is restricted to a local file reference.

1.7. count

Usage: `hadoop fs -count [-q] <paths>`

Count the number of directories, files and bytes under the paths that match the specified file pattern. The output columns are:

`DIR_COUNT, FILE_COUNT, CONTENT_SIZE FILE_NAME.`

The output columns with `-q` are:

`QUOTA, REMAINING_QUOTA, SPACE_QUOTA, REMAINING_SPACE_QUOTA,
DIR_COUNT, FILE_COUNT, CONTENT_SIZE, FILE_NAME.`

Example:

- `hadoop fs -count hdfs://nn1.example.com/file1
hdfs://nn2.example.com/file2`
- `hadoop fs -count -q hdfs://nn1.example.com/file1`

Exit Code:

Returns 0 on success and -1 on error.

1.8. cp

Usage: `hadoop fs -cp URI [URI ...] <dest>`

Copy files from source to destination. This command allows multiple sources as well in which case the destination must be a directory.

Example:

- `hadoop fs -cp /user/hadoop/file1 /user/hadoop/file2`
- `hadoop fs -cp /user/hadoop/file1 /user/hadoop/file2 /user/hadoop/dir`

Exit Code:

Returns 0 on success and -1 on error.

1.9. du

Usage: `hadoop fs -du URI [URI ...]`

Displays aggregate length of files contained in the directory or the length of a file in case its just a file.

Example:

```
hadoop fs -du /user/hadoop/dir1 /user/hadoop/file1
hdfs://nn.example.com/user/hadoop/dir1
```

Exit Code:

Returns 0 on success and -1 on error.

1.10. dus

Usage: `hadoop fs -dus <args>`

Displays a summary of file lengths.

1.11. expunge

Usage: `hadoop fs -expunge`

Empty the Trash. Refer to [HDFS Architecture](#) for more information on Trash feature.

1.12. get

Usage: `hadoop fs -get [-ignorecrc] [-crc] <src> <localdst>`

Copy files to the local file system. Files that fail the CRC check may be copied with the `-ignorecrc` option. Files and CRCs may be copied using the `-crc` option.

Example:

- `hadoop fs -get /user/hadoop/file localfile`
- `hadoop fs -get hdfs://nn.example.com/user/hadoop/file localfile`

Exit Code:

Returns 0 on success and -1 on error.

1.13. getmerge

Usage: `hadoop fs -getmerge <src> <localdst> [addnl]`

Takes a source directory and a destination file as input and concatenates files in src into the destination local file. Optionally addnl can be set to enable adding a newline character at the end of each file.

1.14. ls

Usage: `hadoop fs -ls <args>`

For a file returns stat on the file with the following format:

```
permissions number_of_replicas userid groupid filesize  
modification_date modification_time filename
```

For a directory it returns list of its direct children as in unix. A directory is listed as:

```
permissions userid groupid modification_date modification_time  
dirname
```

Example:

```
hadoop fs -ls /user/hadoop/file1
```

Exit Code:

Returns 0 on success and -1 on error.

1.15. lsr

Usage: `hadoop fs -lsr <args>`

Recursive version of ls. Similar to Unix `ls -R`.

1.16. mkdir

Usage: `hadoop fs -mkdir <paths>`

Takes path uri's as argument and creates directories. The behavior is much like unix `mkdir -p` creating parent directories along the path.

Example:

- `hadoop fs -mkdir /user/hadoop/dir1 /user/hadoop/dir2`
- `hadoop fs -mkdir hdfs://nn1.example.com/user/hadoop/dir`
`hdfs://nn2.example.com/user/hadoop/dir`

Exit Code:

Returns 0 on success and -1 on error.

1.17. moveFromLocal

Usage: `dfs -moveFromLocal <localsrc> <dst>`

Similar to [put](#) command, except that the source `localsrc` is deleted after it's copied.

1.18. moveToLocal

Usage: `hadoop fs -moveToLocal [-crc] <src> <dst>`

Displays a "Not implemented yet" message.

1.19. mv

Usage: `hadoop fs -mv URI [URI ...] <dest>`

Moves files from source to destination. This command allows multiple sources as well in which case the destination needs to be a directory. Moving files across filesystems is not permitted.

Example:

- `hadoop fs -mv /user/hadoop/file1 /user/hadoop/file2`
- `hadoop fs -mv hdfs://nn.example.com/file1`
`hdfs://nn.example.com/file2 hdfs://nn.example.com/file3`
`hdfs://nn.example.com/dir1`

Exit Code:

Returns 0 on success and -1 on error.

1.20. put

Usage: `hadoop fs -put <localsrc> ... <dst>`

Copy single src, or multiple srcs from local file system to the destination filesystem. Also reads input from stdin and writes to destination filesystem.

- `hadoop fs -put localfile /user/hadoop/hadoopfile`
- `hadoop fs -put localfile1 localfile2 /user/hadoop/hadoopdir`
- `hadoop fs -put localfile
hdfs://nn.example.com/hadoop/hadoopfile`
- `hadoop fs -put - hdfs://nn.example.com/hadoop/hadoopfile`
Reads the input from stdin.

Exit Code:

Returns 0 on success and -1 on error.

1.21. rm

Usage: `hadoop fs -rm URI [URI ...]`

Delete files specified as args. Only deletes non empty directory and files. Refer to `rmdir` for recursive deletes.

Example:

- `hadoop fs -rm hdfs://nn.example.com/file
/user/hadoop/emptydir`

Exit Code:

Returns 0 on success and -1 on error.

1.22. rmr

Usage: `hadoop fs -rmr URI [URI ...]`

Recursive version of delete.

Example:

- `hadoop fs -rmr /user/hadoop/dir`
- `hadoop fs -rmr hdfs://nn.example.com/user/hadoop/dir`

Exit Code:

Returns 0 on success and -1 on error.

1.23. setrep

Usage: `hadoop fs -setrep [-R] <path>`

Changes the replication factor of a file. -R option is for recursively increasing the replication factor of files within a directory.

Example:

- `hadoop fs -setrep -w 3 -R /user/hadoop/dir1`

Exit Code:

Returns 0 on success and -1 on error.

1.24. stat

Usage: `hadoop fs -stat URI [URI ...]`

Returns the stat information on the path.

Example:

- `hadoop fs -stat path`

Exit Code:

Returns 0 on success and -1 on error.

1.25. tail

Usage: `hadoop fs -tail [-f] URI`

Displays last kilobyte of the file to stdout. -f option can be used as in Unix.

Example:

- `hadoop fs -tail pathname`

Exit Code:

Returns 0 on success and -1 on error.

1.26. test

Usage: `hadoop fs -test [-ezd] URI`

Options:

- e check to see if the file exists. Return 0 if true.
- z check to see if the file is zero length. Return 0 if true.
- d check to see if the path is directory. Return 0 if true.

Example:

- `hadoop fs -test -e filename`

1.27. text

Usage: `hadoop fs -text <src>`

Takes a source file and outputs the file in text format. The allowed formats are zip and TextRecordInputStream.

1.28. touchz

Usage: `hadoop fs -touchz URI [URI ...]`

Create a file of zero length.

Example:

- `hadoop -touchz pathname`

Exit Code:

Returns 0 on success and -1 on error.